

```

<0716> 100 '      ****      Bank-Dump      ****
<0AA5> 110 ' CPC 664 mit dk'tronics 64KB RAM
<015D> 120 MODE 2
<09D2> 130 LOCATE 27,10:INPUT"Bank-Nr.          (De
z.) : ",ba
<0CBB> 140 IF ba<=0 OR ba>=5 THEN CLS:ba=0:GOTO
130
<0C40> 150 LOCATE 27,12:INPUT"Anfangsadresse (D
ez.): ",a1
<0130> 160 CLS
<0ACD> 170 WINDOW#0,1,80,4,19:WINDOW#1,1,80,1,3
:WINDOW#2,1,80,23,23:WINDOW#4,1,80,20,20
<049A> 180 PRINT#4,STRING$(50,"-")
<1053> 190 PRINT#1:PRINT#1,"Adresse          AS
CII-Text          Bank-Nr.:";ba
<04AB> 200 PRINT#1,STRING$(50,"-")
<02C9> 210 b=0
<033E> 220 in%=0
<1912> 230 |PEEK,ba,a1,@in%:IF in%>31 AND in%<=
127 THEN in$=CHR$(in%)ELSE in$="."
<0AC6> 240 PRINT USING"#####";a1::PRINT USING
"#####";in%;
<02E6> 250 PRINT"          ";
<0513> 260 PRINT USING"\          \";in$;
<00D4> 270 PRINT
<2128> 280 a1=a1+1:IF a1=16384 THEN PRINT#2,"
Bankende erreicht ":FOR n=1 TO 3000:NEX
T n:CLS:CLS#1:CLS#2:CLS#4:WHILE INKEY$<>
"":WEND:GOTO 130
<0B10> 290 b=b+1:IF b>15 THEN b=0:GOTO 310
<01F1> 300 GOTO 220
<178B> 310 PRINT#2,"<<< Neuanfang mit Taste a !
Sonst eine andere Taste druecken >>>"
<08FA> 320 a$=UPPER$(INKEY$):IF a$="" GOTO 320
<08B9> 330 IF a$="A"THEN CLS:CLS#1:CLS#2:CLS#4:
GOTO 130
<0368> 340 CLS:CLS#2:GOTO 220

```