

```

10 MODE 1:PRINT"KRAFT:":PLOT 112,392,1 [3627]
15 DRAW 630,392:PLOT 112,388:DRAW 630,388: [3014]
LOCATE 40,25:PRINT CHR$(250);
20 WINDOW 1,40,3,24:FOR a=1 TO 10:PRINT"VE [4264]
RSUCH";a:PLOT 0,0:DRAW 639,0,1
25 PRINT">":CALL &BB06:CLS:PLOT z,2,0:z=CI [2294]
NT(RND*500)+2:PLOT z,2,1
30 PRINT"WINKEL":PRINT">":CALL &BB06:FOR b [4228]
=2 TO 630:PLOT b-2,200,0
35 PLOT b,200,1:a$=INKEY$:IF a$=""THEN NEX [2716]
T:ELSE GOTO 40
40 PRINT"KRAFT":PRINT">":CALL &BB06:FOR d= [4385]
112 TO 630:PLOT 112,390
45 DRAW d,390,1:a$=INKEY$:IF a$=""THEN NEX [4163]
T:ELSE GOTO 50
50 PLOT 112,390:DRAW 630,390,0:CLS:x=630-( [3533]
(630-b)/630)*d:y=200*(630-x)/(630-b)
55 o=(y/(630-x))*2:y=0:FOR e=630 TO x STEP [5280]
-2:y=y+o:PLOT r,s+10,0:r=e:s=y
60 PLOT e,y+10,1:NEXT:PLOT r,s+10,0:o=y/(( [2782]
630-r)/3)
65 FOR e=r-1 TO r-((630-x)/3) STEP -1.5:y= [4740]
y-1.5*o:PLOT r,s,0:r=e:s=y

```

```
70  PLOT e,y,1:NEXT:PLOT r,s,0:t=CINT(ABS(z [3619]
-e)):CLS:PRINT"PKT:";t:p=p+t
75  PRINT">":CALL &BB06:CLS:NEXT:PRINT"ERGE [3145]
BNIS:";p
```

Listing Zielwurf